



Technical Administrator User Guide

Version 2.2

March 2019



DISCLAIMERS

KPMG

KPMG LLP ("KPMG"), an Audit, Tax and Advisory firm (kpmg.ca) and a Canadian limited liability partnership established under the laws of Ontario, is the Canadian member firm affiliated with KPMG International Cooperative ("KPMG International").

KPMG member firms around the world have more than 200,000 professionals, in 154 countries and territories.

The independent member firms of the KPMG network are affiliated with KPMG International, a Swiss entity. Each KPMG firm is a legally distinct and separate entity, and describes itself as such.

Informational Purposes

The information contained herein is of a general nature pertaining to the specific product or products described herein and is not intended to address the circumstances of any particular individual or entity. Such information is provided for general informational purposes only, and KPMG neither warrants nor represents that the information contained herein is accurate, complete or appropriate for any specific purpose. Although we endeavor to provide accurate and timely information, there can be no guarantee that such information is accurate as of the date it is received or that it will continue to be accurate in the future. No one should act on such information without appropriate professional advice after a thorough examination of the particular situation.

Copyright

Laws in Canada and other countries preserve for KPMG and its applicable affiliates, subsidiaries, related parties and licensors exclusive rights for copyrighted computer programs, including the exclusive right to copy or reproduce in any form the copyrighted computer program. Accordingly, this documentation, and any copyrighted KPMG computer programs contained in the KPMG products described in this documentation, including without limitation VeloCITY 365 (collectively, the "KPMG Programs" and, collectively with the documentation, the "KPMG Material") may not be copied or reproduced in any manner without the prior express written permission of KPMG.

Restrictions

The KPMG Material is the property of KPMG. It is furnished under a license, services and/or engagement agreement with you and may be used and/or disclosed only in accordance with the terms of such agreement(s). The KPMG Material consists of copyrighted materials. Making unauthorized copies is prohibited by law. No part of the KPMG Material may be reproduced, transmitted, transcribed, stored in a retrieval system, or translated into any language or computer language, in any form or by any means, without the prior written permission of KPMG.

Accuracy

While reasonable efforts have been made to assure the accuracy of this documentation, KPMG assumes no liability resulting from any inaccuracies or omissions in this documentation, or from the use of any information obtained herein. KPMG reserves the right to make changes to the KPMG Material or any part thereof to improve reliability, function, or design, and reserves the right to revise this documentation and to make changes from time to time in content hereof with no obligation to notify any person of revisions or changes. KPMG does not assume any liability arising out of the application or use of any product described herein; neither does it convey license under its patent rights of others.

Trademarks

The KPMG name and logo are registered trademarks or trademarks of KPMG International Cooperative ("KPMG International"), and are used under license by KPMG. Microsoft, Windows, Microsoft Dynamics 365 are registered trademarks of their respective owners. All other product or service names are the property of their respective owners. Nothing herein or in the KPMG Material grants to you any rights in or to any trademark whatsoever, whether owned by KPMG International or any third party.



Table of Contents

ntroduction to VeloCITY 365	5
VeloCITY 365 Configuration	6
Deployment, Promotions and Hot fixes	6
Interaction Type (SR) Administration	8
Creating Interaction Types	9
SharePoint Configuration	14
Editing Interaction Types	15
Creating Tags	18
Understanding Interaction Type Settings	19
Setting up Notifications and Email	21
Managing Notification Workflows	21
Setting up Email	23
Setting up Routing and SLAs	25
Routing	25
Managing SLAs	27
Managing Work Order Administration and Automation	28
Managing Translations	29
CRM Label Translations	30
Setting up CRM Security	35
Overview of CRM Security Roles	35
Assigning Security Roles	40
ArcGIS Configuration	41
Configuring the ESRI Settings	44
Setting up the ESRI Server	44
Configuring the ESRI Map	46
Configuring the ESRI Map Layers	55
Configuring the ESRI Layer Field Mappings	58
Configuring the ESRI Entity Field Mappings	59
Configuring Service Areas	60
Configuring Icons	60
Map Settings for Agent Console	61




Map Settings for Portal Service Request Map	62
Citizen Engagement Portal Configuration	63
Portal Authentication	63
Web Roles	64
Branding and Theming	66
Updating Web Files	66
Updating Web Templates	67
Site Settings	68
Portal Content	70
How to edit page content	70
How to edit navigation	70



Introduction to VeloCITY 365

VeloCITY 365 by KPMG provides automated workflows that enable municipalities to manage citizen inquiries and service requests in the cloud. Velocity is built on the Microsoft Dynamics 365 platform, and provides a Citizen Engagement Portal that citizens can access to search and find information on municipal programs and services. Call center agents can efficiently document citizen inquiries, identify duplicate requests, and route service requests to the appropriate department for action and follow-up, while tracking the progress of the request through to completion.





VeloCITY 365 Configuration

Deployment, Promotions and Hot fixes

The process for deploying, promoting and applying hot fixes to VeloCITY 365 follows a well-documented path from Development to Production. It is expected this methodology will be followed with separate environments for each phase of the development cycle. All new work or changes are made within the Development Environment. The changes are promoted to the Test Environment for testing and approval/rejection. Once these changes have been approved, they are promoted to the Production Environment. This path not only ensures the changes to the product are successful applied, it also ensures the deployment/promotion process is complete and produces the desired results.



When planning for an upgrade, promotion or hotfix there are 2 categories of information that needs to be considered, namely customizations and data.


- Customizations are changes that have been made to the Dynamics 365 platform, i.e., entities, option sets, dashboards.
- Data are business records, i.e., contacts, cases, information that drives the portal (Content Snippets, Web Links etc.)

Safe	Use Caution	Avoid
Changes to content are considered safe.	Changes to the Production	Removing any
Examples include:	environment that involve the creation	application data as
Content to the Deflection content on an	of new application data as all actions	recovery is time
Interaction Type	are immediate, are visible to a large	consuming and not
Content within names, titles, text or	audience and having incorrect or	always possible.
summaries on Web Pages	incomplete data can have disastrous	
Content within titles, descriptions or URLs of	consequences.	
Web Links		
Values on Content Snippets		
Values on Site Settings		



When agreeing to a Hot Fix, consideration must be given to how the change will be merged back into the Development environment. For large and/or complex changes, the recommended methodology is to use Microsoft's Configuration Migration Tool. The conditions that need to be considered include:

- New records must be copied back to the Development environment using an ID- matching data copy tool
- Content changes can be copied back to the Development environment using copy-paste or IDmatching data copy tool
- Schema (customizations) changes should be copied back to the Development environment using a transport solution
- Customizations should be copied back to the Development environment using a transport solution or by manual reproduction (Not recommended, but possible)
- A subsequent deployment is needed from the Development environment to the Test/UAT environment






Interaction Type (SR) Administration

Interaction Type records hold all the configuration and metadata needed for the creation of a Service Request Intake form. Setting up an Interaction Type enables the creation of a unique service request form for each type by selecting the appropriate checkboxes and option values.

The creation of Interaction Types has been simplified through an Interaction Type Wizard. The wizard removes complexity while enforcing consistent design patterns, and enabling the quick setup of:

- Entities, fields, forms, views, sitemap
- Portal integration
- ArcGIS integration
- Routing
- Duplicate detection





Creating Interaction Types

To create an Interaction Type:

Navigate to VeloCITY 365 \rightarrow Settings \rightarrow Interaction Types. The Interaction Type list displays. Click New. The New Interaction Type form displays. Complete the form as required. Click Save.



<u>TIP</u>: The wizard has automated many of the manual steps, but you will need to wait while it completes the setup. The setup progress can be monitored under the Automation Status column; however, the statuses will appear very briefly. The estimated total time to complete an Interaction Type varies from 3-5 minutes depending upon the usage of the current system and the chosen configuration (Interaction Type settings)

Admin Setup	Description
Display Name	The name of the Interaction Type as it will display on the Portal and the CRM
Plural Name	The plural form of the Interaction Type as it will display on the CRM Lists, Views and Related Names.
Parent Interaction Type	The Interaction Type under which this type will display on the portal. If this is the top most Interaction Type, leave this field blank. If this is a secondary Interaction Type, select the Interaction Type one above.
Business Unit	By defining a Business Unit(s), you can establish a "hierarchical-like" relationship to facilitate reporting for service requests at the Business Unit level.
Add to CRM Solution	Creates the Entity within the selected solution for Parent Interaction Types. TIP: All Interaction Types must be added to a CRM solution. If adding a child interaction, it is added to the parental entity using the Parent Interaction Type field.
Schema Name	This is a non-editable, locked field that is populated based on the Entity name.
Enable Rollup Activation	This section is not configurable and is locked. It is used to facilitate the rollup of the specified interaction type.
Disable Creation in Agent Console	Defines whether or not the interaction type is allowed for creation in the Agent Console.
Entity Schema Name	This is a non-editable, locked field that is populated based on the Entity name and is updated to the Parent Interaction schema if a Parent Interaction Type is selected.



File Upload	Description
Enable File Upload	Defines whether or not the interaction type will allow files and notes to be added to the service request. Note: Once enabled, this setting cannot be disabled.
File Upload Location Displays when Enable File Upload is enabled	There are two options for file locations, namely storing the files within the "Notes" section of the cases inside Dynamics, or with the built in SharePoint integration. Documentation on how to configure the SharePoint option is found in the next section of this documentation.

Portal Settings	Description
Show on Portal	Defines if this service request type is visible in the portal.
Cases are Public	Determines if case types appear in citizen search results.
Enable for Intake	Determines if this type of request can be submitted via the portal. TIP: Must be enabled if sub-types are associated as the value is inherited by the sub-types.
Hide Custom Fields	Determines if the custom fields will be seen on the Portal. If selected, all custom fields will be seen within CRM but not on the Portal.

Portal Tile Icon	Description
Portal Icon Type Displays when Show on Portal is enabled	Determines if the type of icon used on the portal will be CSS Class Icon or an Image URL icon.
Portal Icon Value Displays when a value is selected with the Portal Icon Type field.	Determines the icon seen when a value is entered into the Portal Icon Type field. If Image URL is selected, the URL for that image must be entered. If CSS class is selected, the value for the class must be entered.

Enable Deflection Page Displays when Show on Portal is	Determines if a deflection page will display.
enabled	TIP: A deflection page helps to determine if the Service Request is needed. The submission of the request may be prevented if the citizen is diverted to an alternate path. Refer to the Deflection Options



Deflection Options	Description
Show Subtype Widget Displays when Enable Deflection Page is enabled	Determines if the child related service requests display on the portal's initial service request page. Related service types are identified through tags.
Show Related Interaction Types Widget Displays when Enable Deflection Page is enabled	Determines if the related service requests display on the portal's initial service request page. Related service types are identified through tags.
Show Related Alerts Widget Displays when Enable Deflection Page is enabled	Determines if the related alerts display on the portal's initial service request page. Related alerts are identified through tags.
Show Related Cases Widget Displays when Enable Deflection Page is enabled	Determines if the potentially related service requests display on the portal's initial service request pages. Service requests in a status of "Waiting for Details" or "On Hold" are not displayed.
Show Related KB Articles Widget Displays when Enable Deflection Page is enabled	Determines if the potentially applicable knowledgebase articles display on the portal's initial service request page.
Show SLA Widget Displays when Enable Deflection Page is enabled	Determines if the expected response and resolution times display on the portal's initial service request page. TIP: Refer to the Response By and Resolution By fields below. If no values are entered into the fields, the widget will display but will display "Not Set".
Button Text Displays when Show on Portal is enabled	Determines the label on the button on the Service Request Deflection page. The default text is Create 'Interaction Display Name.'

Contact Details	Description	
Enable Contact	Determines if the contact information may be requested for the Service Request. If not selected, the Allow Anonymous Portal Submission becomes selected and locked.	
Default Customer	Determines the default contact if citizens are permitted to submit anonymous requests.	
	TIP: Every Interaction Type must have an associated contact. As a result, a default contact must be created to whom all the anonymous submissions are associated. For example, Default Anonymous	



Allow Anonymous Portal Submission	Determines if service requests may be submitted anonymously.
	TIP: Every request must have an associated contact. As a result, all the anonymous submissions will be associated with the value entered into the Default Customer field.
Require Contact Details on Portal Displays when Allow Anonymous Portal Submission is enabled	Determines if the citizen must be either authenticated or provide contact details to request this Interaction Type.

Location Details	Description
Enable Location	Determines if location information will be requested for the Service Request. This is selected by default.
Location Required	Determines if location information will be required for the Service Request.
Allow Location Override	Determines if location selected on map can be manually overridden by entering the specific address in the address fields on case form. If unchecked, users must identify the address using the Point, or Intersection functionality when creating a service request.
Enable Duplicate Detection (CRM)	Determines if duplicate service requests entered in the Agent Console will be identified. This is selected by default.
Enable Duplicate Detection (Portal)	Determines if duplicate service requests entered on the Portal will be identified.
Duplicate Detection Units	Determines if the duplicate detection range will be measured in miles or kilometers.
Duplicate Detection Range	Determines the range of the duplicate detection. TIP: The values must be entered as decimal with 2 decimal places and the smallest possible value = 0.01. The equivalent of 10 metres if the units are kilometers or 52.8 feet if the units are miles.
Max Results to Show in Portal Displays when Enable Duplicate Detection (Portal) is enabled	Determines the maximum number of duplicate records to display within the portal.

Service Areas	Description
Service Areas	Lists the properties of the service areas associated with the interaction type. These service areas are created in the ESRI Map settings and their configuration is documented in that section of this User Guide.



Map Settings	Description
CRM Map Settings	Determines the map that will display within CRM for this service request type. The map lookup is populated from ESRI Settings within Connect 365
Portal Map Settings	Determines the map that will display within the portal when the citizen is reporting this service request type. The map lookup is populated from ESRI Settings within Connect 365
Map Overlay / Color Type	Determines the type of map overlay that will be used on the portal map.
Map Overlay / Color Value	Determines the map overlay color that will be used on the portal map.

Routing and SLAs	Description		
Owning Team	Determines to which team the service request will be routed. TIP: For more information on routing, refer to the Routing and SLA section. The teams are created within Dynamics 365 → Settings → Security → Teams		
Queue	Determines the Queue to which the request will be added.		
Response By	Determines the expected time for a response to the service request.		
Resolution By	Determines the expected time for a resolution to the service request.		

Custom Fields	Determines if an interaction-specific field will display on the portal's Issue Details page when requesting a Service Request.
Permissions	This is a collection of user defined permissions indicating which security roles have read-only or full access. [Only visible after the interaction type has been created]
Related Items & Tags	Determines if an additional tag will be associated with this type of Service Request.
Child Interaction Types	Open the New Interaction Type form and automatically associates the new interaction as a child of the current record.
Rollup Mappings	Displays on the Interaction Type record after it has been created. The Interaction Type wizard creates the mappings automatically. Changing any of these mappings is NOT RECOMMENDED.



SharePoint Configuration


If when setting up a specific Interaction Type, you enabled "file upload" and you identified SharePoint as the "file upload location" (Both these settings are in the Admin section when setting up an Interaction Type), then there is additional configuration required. This section describes how to complete that additional configuration.

Reconfigure the Velocity Flow "ABS – Move Note Attachment to SharePoint..." to work with your environment. By default, and if not already done, this flow needs its connection initialized before enabling it. (You need to be an admin for the CRM instance you are configuring)

- i.Visit https://web.powerapps.com
- ii.On the left menu, click Solutions
- iii. Open the Adoxio Interaction Flows solution and open the ABS Move Note Attachment to SharePoint flow.
- iv.Click on Edit (after making sure the flow is not enabled).
- v.For each block in the flow that has an exclamation mark on it (suggesting a bad connection) fix that block by adding a new valid connection.
- vi.Enable the Flow.

If you selected SharePoint as your target location, you need to follow the following steps to enable SharePoint.

- 1. Configuring the SharePoint Side:
 - a. Create a site on SharePoint and note the site address.
 - b. Assign users as owners or contributors to the site as needed.
- 2. Configuring CRM Side:
 - a. Go to Settings -> Document Management
 - b. Click on Enable Server-Side SharePoint Integration if not already enabled.
 - c. Use the site you got from step (1).
 - d. Open Document Management Settings.
 - e. Enable Case for Document Management if not already enabled.
- 3. Configuring the Portal Side:
 - a. Open the portal admin center (as global admin).
 - b. Enable SharePoint integration as shown in the images below:





Editing Interaction Types

Interaction Types are completely editable and if using a self-service portal, the changes are seen as soon as CRM has completed its updates.

To edit an Interaction Type:

- Navigate to VeloCITY 365 → Interaction Types.
- The Interaction Type grid displays.
- Select the required Interaction Type.
- The Interaction Form displays.
- Update the required fields.
- Click Save.

The fields added during the creation of an Interaction Type are outlined below.

Managing CRM Entity Detail

The following fields are added during the creation of the Interaction Type.

CRM Entity Detail	Description	
Business Process	Determines the business process flow for the interaction type. The ABS – Case – Default Business Process is associated by default. Refer to the Business Processes section within this document for more information on creating alternate business process flows.	
Agent Details Form	The default Interaction Type-specific details form created by the system.	
Quick View Form	The default Interaction Type-specific View created by the system.	
Manager Form	The default Interaction Type-specific manager form created by the system.	
Regenerate CRM Forms	Enables the regeneration of the CRM form when changes have been made. NOTE: Any customizations done to any related CRM forms such as adding fields, rearranging fields, etc. will be LOST as a result of this regeneration.	
Regenerate Portal Forms	Enables the regeneration of the Portal form when changes have been made. NOTE: Any customizations done to any related CRM forms such as adding fields, rearranging fields, etc. will be LOST as a result of this regeneration.	



Managing Custom Fields

The Custom Fields sub-grid is added during the creation of the Interaction Type. The sub-grid enables the addition of custom fields during the reporting of a service request. The custom fields display on the portal's Issue Details page.

To add a custom field:

- Navigate to the Custom Field sub-grid and click the +.
- The sub-grid lookup displays.
- Click New.
- The New Interaction Type Custom Field form displays.
- Enter the name of the custom field in the Display Name field.
- The Parent Interaction Type field defaults to the current Interaction Type.
- The association can be edited.
- The Schema Name is a locked field and will be created based on the value within the Display Name.
- Select the required type of field from the Type option set.

Additional fields display based on the option set selection.

- Multiple Lines of Text No additional input required.
- String No additional input required.
- Boolean No additional input required.
- Integer- No additional input required.
- Decimal—No additional input required.
- Date/Time No additional input required.
- Date No additional input required.
- Option Set fields display for the addition of option set values. Be sure to save the option set values (the save icon on top of the option set field) before closing the form.
- Global Option Set Global Option Set Lookup displays. Select the required value.
- Click Save. The Interaction Detail form displays.
- Click Save and Close

Managing Permissions

The permissions sub-grid is available after the interaction type has been created. Creating a permission record will grant read-only or full access permissions to the security role for the interaction type. This must be done in order for a given security role to access the service request records in CRM.

To add a Permission:

- Navigate to the *Permissions* sub-grid and click the +.
- The New Interaction Type Role Permission form displays.
- Select a security role to be granted access.
- Select the access level, Read Only or Full Access
- Click Save.



Managing Related Items & Tags

The Related Tags and Child Interaction Types sub-grids are added during the creation of the Interaction Type. The sub-grids enable the association of related knowledge base articles and service requests as well as other child Interaction Types during the reporting of a service request. The custom fields display on the portal's Issue Details page.

To add a Related Item:

- Navigate to the Related Item sub-grid and click the +.
- The sub-grid lookup displays.
- Click New.
- The New Tag form displays.
- Enter the name of the tag.
- Enter a tag description.
- Identify a parent Tag, if applicable.
- Click Save.
- The Child Tags and Associations sub-grids enable.
- Select the appropriate Child Tags, Knowledge Articles, Alerts and Interaction Types.
- Click Save.

Managing Rollup Mapping

The Rollup Mappings are added during the creation of the Interaction Type. While some of the fields are not locked, *it is NOT recommended that any of the fields be edited*.

Managing Multi-Lingual

The Multi-Lingual fields are added during the creation of the Interaction Type. There is only one field that requires configuration: Enable Multilingual. Selecting these checkboxes creates the base content snipped that is required to implement the multi-lingual functionality. Once these are created, the content snippets should be updated in the interaction wizard with the associated names (title, deflection page text & create button text) based on their business needs.



Creating Tags

Creating tags is very important within VeloCITY 365 as tags impact the display of Interaction Types, Alerts, Knowledge Base Articles, and Search results.

When you create a tag a matching Content Snippet will also be created. The Content Snippet will contain auto-generated sample content in the Value field. The content must be overwritten.

If Content Snippet is accidentally deleted it can be easily re-created by matching the original name.




TIP: A tag must be active before it can be edited.

To create a Tag:

- Navigate to Velocity 365 → Tags
- Click New.
- The New Tag form displays.
- Enter the Tag Name.
- This name will display within both VeloCITY 365 and any associated portals.
- If this is a child tag, select the Parent Tag name.
- Complete the additional sections, as required.
- Click Save & Close.

Section Name		Description
Child Tags		Add any tag records that should be associated under the current tag. Once added, the tag displays in the sub-grid.
Associations		
	Knowledge Articles	Add any Knowledge articles that should be associated with the current tag. Once added, the article name displays in the sub-grid. Parent tags are able to see all child associations, but child tags cannot see other parent or child associations.
	Alerts	Add any Alerts that should be associated with the current tag. Once added, the alert name displays in the sub-grid. Parent tags are able to see all child associations, but child tags cannot see other parent or child associations.
	Interaction Types	Add any Interaction Types that should be associated with the current tag. Once added, the Interaction Type name displays in the sub-grid. Parent tags are able to see all child associations, but child tags cannot see other parent or child associations.





Understanding Interaction Type Settings

Widgets

VeloCITY 365 has created five (5) of the most requested optional functionality items as widgets. The widgets can be added to an Interaction Type by simply selecting the appropriate checkbox. The five default widgets that can be added to any Interaction Type are as follows:

Name	Description	
Show Subtype Widget	Determines if the child related service requests display on the portal's initial service request page. Related service types are identified through tags.	
Show Related Interaction Types Widget	Determines if the related service requests display on the portal's initial service request page. Related service types are identified through tags.	
Show Related Alerts Widget	Determines if the related alerts display on the portal's initial service request page. Related alerts are identified through tags.	
Show Related Cases Widget	Determines if the potentially related service requests display on the portal's initial service request page.	
Show Related KB Articles Widget	Determines if the potentially applicable knowledgebase articles display on the portal's initial service request page.	



Show SLA Widget	Determines if the expected response and resolution times display on the portal's initial service request	
	page. TIP: Refer to the Response By and Resolution By fields below. If no values are entered into the fields, the widget will display but will display "Not Set".	

The Default Widgets share metadata across Interaction Types and this distributes the metadata to the parent/child type family.

Business Processes

VeloCITY uses the business process flows included with Dynamics 365. Business processes are unique to each implementation and situation, and as a result need to be implemented to suit each situation and attached to the appropriate interaction type. Information on creating business process flows can be found by searching "business process flows overview" on the Microsoft documentation site or <u>click here</u>.

Managing Forms

Forms are included within VeloCITY365 but new custom forms or custom fields can be created on the existing forms.

Information on creating new forms can be found by searching "Create a quick view form" on the Microsoft documentation site or <u>click here</u>. Be sure to link the new form to an Interaction Types.

Information on editing the existing forms can be found by searching "Work with the form editor" on the Microsoft documentation site or click here. Be sure to link the new form to an Interaction Types.



Setting up Notifications and Email

Notifications and Emails are based on Dynamics 365 workflows and the VeloCITY 365 Mailer queue. Workflows can be configured to your needs, i.e., service request submissions, service request status changes or service request merges.

Managing Notification Workflows


Velocity365 includes notification workflows that have been configured to respond to system activity and automatically send notifications to either internal recipients, i.e., System Administrators or Velocity365 Administrators or external recipients, i.e., citizens. The included workflows are:

Workflow	Audience	Description
Velocity 365 - Send Status Change Update Email to SR Subscribers	External	Sends personalized notification to each subscriber when status is changed on a case.
ABS - Case - Merge All Potential Duplicates	External	Sends notification to customer of duplicate cases being merged (using "Velocity Case Merged Template").
ABS - Case - Merge Into Identified Parent	External	Sends notification to customer of duplicate cases being merged (using "Velocity Case Merged Template").
ABS - Case - Notify Customer When Case is Canceled	External	Sends personalized notification to customer when case is cancelled.
ABS - Case - Clone Service Request	Internal	Sends generalized notification to internal team when case is changed from one Interaction Type to another.

The Velocity365 workflows can be configured to suit needs your needs and new workflows can be added.



All included notifications are sent from the Velocity 365 Mailer queue: Settings \rightarrow Email Configuration \rightarrow Mailboxes \rightarrow Active Queue Mailboxes View



More information on the configuration of workflows can be found by going to Dynamics 365 Documentation information site or click here.



Setting up Email

Velocity 365's included workflows include dynamically-created emails specific to the triggering system activity. The included emails are within the table below:


Name	Audience	Description
Velocity 365 - Send Status Change Update Email to SR Subscribers	External	Sends personalized notification to each subscriber when status is changed on a case.
ABS - Case - Merge All Potential Duplicates	External	Sends notification to customer of duplicate cases being merged (using "Velocity Case Merged Template").
ABS - Case - Merge Into Identified Parent	External	Sends notification to customer of duplicate cases being merged (using "Velocity Case Merged Template").
ABS - Case - Notify Customer When Case is Canceled	External	Sends personalized notification to customer when case is cancelled.
ABS - Case - Clone Service Request	Internal	Sends generalized notification to internal team when case is changed from one Interaction Type to another.

The emails are all generated using the out of the box workflows and sent from the Velocity 365 Mailer queue. The queue can be mapped to any email address, but if mapped to Exchange Online, the email address for the Mailer must belong to a licensed Office 365 user or to a shared mailbox. A typical email address for sending email is noreply@mycity.com.

If a different sender is preferred for a specific email, each of the workflows can be modified as required.



When deployed the default sender is Velocity 365 Mailer.



More information can be found by going to Dynamics 365 Documentation information site:

- For information on email templates, click here.
- For information on connecting Dynamics 365 (online) to Exchange Online, click here.
- For information on connecting Dynamics 365 (online) to Exchange Server (on-premises), click here.

Changing the default sender (mailer queue)

To change the default sender:

- Navigate to Settings → Processes.
- The All Processes view of the Process form displays.
- Navigate to the required process.
- The process detail form displays.
- Click the Set Properties button to the right of the field to be updated, i.e., Send English Email.
- The email template displays
- If the Set Properties button is not displayed, deactivate the process.
- Update the Sender within the From field's lookup.
- Click Save and Close.
- Click Activate, if required.
- The Process Activate dialog displays, confirm the activation.



Setting up Routing and SLAs

Routing is planning which person or team will own the resolution of a specific Interaction Type and the amount of time within which a response and resolution is expected, i.e., If a service request is submitted for a pothole, it could be routed to the Road Maintenance team and a response is expected within 3 days with a resolution within 2 weeks.

For more information on assigning a team and SLAs to an Interaction Type, refer to the Routing and SLAs section of Creating Interaction Types.

Routing

When planning the assignment of an Interaction Type, it is important to understand the concept of teams. While the creation of a team allows for the sharing of information and security roles, there are some constraints that should be considered when planning your Teams as these constraints may impact the ability to promote Interaction Types from one environment to another:

- Business Units, Teams and Queues cannot be copied to or synchronized between environments without either special tools, data manipulation, or cloning environments
- Business Units each have a system-generated default Team with system limitations:
 - Cannot set your own Team as default
 - Cannot delete default Team
 - o Cannot import a Team as default

You can route service requests for a specific interaction type to a specific Team (default or manually configured) and you can route service requests to a Queue (default or manually created). A Team can have one or more queues. If there is more than one queue defined for a specific team, the queues need to be defined in their respective Service Areas.

Example:


If we have a Pothole interaction type, and the city was broken down into 3 regions; namely East, West & Central, and we wanted to route service requests based on the region then we could set up one Team with 3 Queues (East, West & Central). We would also need to define 3 Service Areas (East, West & Central) and then have each of the respective queues defined on the related service areas. The result would be the service requests will be routed based on location (region) and then further to the queue associated to that specific region. Reporting could then be done by Team or alternatively, by Service Area to identify trends or resource levels.

Information on how to set up Service Areas can be found in the "ESRI Map Settings - Setting Up Service Areas"



Setting up a Team:

- Navigate to Settings → Security → Teams.
- The All Teams view of the Teams form displays.
- Click New.
- The New Team form displays.
- Enter the Team Name and Administrator.
- Click Save.
- The Team members sub-grid enables.
- Click the + to add members.
- Click Save.



- Teams each have a system-generated default Queue with system limitations
 - You can define your own Queue as default
 - You can delete the default Queue

NOTE: Be sure to add the appropriate security role to the team members so they can access the service requests once they are assigned.

Setting up a Queue:

- Navigate to Settings → Service Management → Queues
- Click New
- The New Queue form Displays
- Enter the Name and the Description (The default type is Public)
- The owner should be configured to be the Team name established above
- Click the + to add members to the queue
- Click Save



Managing SLAs

Default Service Level Agreement values are provided within VeloCITY365. The values can be modified as required by modifying the xml code. An example of the xml is:

```
· Field Name: Logical name of field to apply to
                                                       <field name="abs responseby">

    abs_responseby

                                                          <option>

    abs_resolutionby

                                                            <value>1</value>
                                                            <label>minutes</label>
· Value: The option set value to map to
• Label: Unit of time (e.g. the "day" in "1 day")
                                                            <interval>30</interval>
  · minute OR minutes
                                                          </option>

    hour OR hours

                                                          <option>

    day OR days

                                                            <value>2</value>
  · week OR weeks
                                                            <label>hour</label>
• Quantity: Length of time (e.g. the "1" in "1 day")
                                                            <interval>1</interval>
                                                          </option>
                                                      </field>
```

Modifying SLA values:


- Navigate to Settings → Customize the System.
- The Default Solution form displays.
- Navigate to Web Resources → abs_/Interaction/xml/ResponseAndResolutionBy.xml.
- The detail form displays.
- Click Text Editor.
- The Edit Content form displays.
- Modify as required and click OK.
- The Edit Content form closes.
- Click Save and close the detail form.



Managing Work Order Administration and Automation

VeloCITY uses the workflows included with Dynamics 365 and are a powerful tool that allows for simple, or complex automation of tasks such as work order automation. The work order workflows are unique to each city and situation, and as a result need to be implemented to suit each situation and attached to the appropriate interaction type.

Workflow	Description
ABS - Case - Cancel active work orders on merge	If associate Case is merged into another Case, associated Work Orders are closed.
ABS - Case - Verify Work Orders are completed	Case cannot be closed if any associated Work Order is open.



Information on creating workflows can be found by searching "Use Workflow processes to automate processes that don't require user interaction" on the Microsoft documentation site or <u>click here</u>.



Managing Translations

Providing VeloCITY 365 in the appropriate language for your area is important. Velocity 365 is multi-lingual for both VeloCITY and Portal users. Alerts matching the user's preferred language are displayed in the Agent Console. Interaction (SR) Types support translations that are common to any custom entity in VeloCITY.

Туре	CE Users	Portal Users
Alerts	✓	√
Content Snippets		✓
CE Customizations	✓	√
Knowledge (KB) Articles	✓	✓
Interaction (SR) Types	✓	✓
Tags		✓
Web Links		✓
Web Pages		✓



CRM Label Translations

There are 3 stages to providing VeloCITY 365 in the appropriate language. There are some duplicate detection and workflow logic to note when translating labels:

- Within calculated fields, VeloCITY 365 uses only the base language.
- Within field labels, the user's preferred language (user interface language) is used if available. If not available, the base language is used.
- Duplicate detection considerations
 - Duplicates are detected from the fields that are in the base language. While it is possible to localize the language for those fields, duplicates will not be detected if the fields are created of updated outside of the base language.
 - This is also true if importing data; only the fields with labels in the base language are used for duplication detection.
 - When import is executed in non-base language, the import fails because update can't be performed in a non-base language.

Provisioning the language pack

It is important to provision the language packs first. If you import translated values for languages that haven't been provisioned, they'll be discarded. The language settings are found within System \rightarrow Settings \rightarrow Administration \rightarrow Languages.

Note: Language settings may take some time to complete.





Enabling Supported Languages

Once a language pack has been provisioned, it must be associated with the portal or it will not display as a language option.

To associate a language:

Navigate to Portals → Websites

Open the appropriate portal and navigate to the Supported Languages sub-grid.

Click the Add Website Language Record button.

The New Website Language form displays.

Complete all the required fields and click Save & Close.

The language displays in the Supported Languages sub-grid and is available for selection when creating a content snippet.

Creating Alerts in Multiple Languages


To create Alerts in multiple languages, an alert must be created in each language (one record per language).


Navigate to Settings → Alerts

Click New. The New Alert form Displays.

Enter the Alert name and enter the language code.

The language code can be found on the Language Settings Dialogue window Dynamics 365 \rightarrow Settings \rightarrow Administration \rightarrow Languages.







Creating Content Snippets in Multiple Languages


To create Content Snippets in multiple languages, an alert must be created in each language (one record per language).


Navigate to Portals → Content Snippets
Click New. The New Content Snippet form Displays.
Enter the required information as well as select the Content Snippet language.
Click Save & Close

For more information on multi-lingual content snippets, refer to



Enabling Supported Languages





Stub Records

These records are created then need to be updated to reflect the proper translation text

Creating Web Links in Multiple Languages

Web Links are the page navigation links that display within the portal's primary and secondary navigation as well as within the footer. A new record is created for each of these web link types for each language enabled on the portal, that is, for the primary navigation record type, 3 different primary navigation records will be created if you have enabled English, French and Spanish.

The translation of the actual web link is a part of the client deployment process or through manual translation through the web page editor.



Translating Knowledgebase Articles into Multiple Languages

To translate existing Knowledgebase Articles,


Navigate to Velocity \rightarrow Customer Service Hub \rightarrow Knowledgebase Articles. The Articles form displays. Select the article to be translated. The article details page displays.


Click Translate. The Create New Translation dialog displays.

Enter the language into which the article should be translated in the Pick a Language field.

Click the Create button. A new version of the article tagged with the new language is created.

The translated article displays as a child association to the originating article.





Completing a Bulk Translation outside of VeloCITY 365

If translating large amount of content or translating by a professional translator, it may be easier to complete the translation outside of VeloCITY. To do this, the content will need to be exported, modified and then imported back into VeloCITY 365.

Exporting data for translation

Go to Settings → Data Management.

Select Export Field Translations.

In the Export Field Translations dialog box, select OK.

All product fields that are marked as localizable by default will be exported. Your internal developers must mark the fields as localizable.


Save the .zip file to your local computer.

Exported text is saved as a compressed file that contains a CrmFieldTranslations.xml that you can open by using Excel. You can send this file to a linguistic expert, translation agency, or localization firm.

The excel file will display Columns A, B and C as well as the column headings for the editable field translations as shaded. Do not change the information that is shaded. Changes within the shaded fields and columns will break the import of the translation file.

The editable fields are displayed below the language code column header, i.e., English = 1033, French = 1036 and Spanish = 3082.





Importing translated data

Go to Settings → Data Management.

Select Import Field Translations.

In the Field Translation Import Jobs page, on the Action toolbar, select Import Field Translations.

In the Import Translated Text dialog box, select Browse, and select the file that you've received from your translation agency.

Select Import. This starts the import job. You can check the status to see if the import has succeeded or failed. After you've imported the translated text, users in your organization will see the data in their preferred language. If a value for the preferred language does not exist, the results will be shown in the user's base language.




Setting up CRM Security

Authenticated portal users are associated with a CRM Contact and must have the appropriate security role assigned.

If using a self-service portal, portal users must be assigned to Web Roles in order to gain permissions beyond unauthenticated users. For more information on portal security within this document, refer to the Web Roles section 64, or click here for Microsoft information

Overview of CRM Security Roles

Security roles are a combination of privileges and access levels for the various entities. They are grouped under different tabs based on their functionality. These groups include: Details, Core Records, Marketing, Sales, Service, Business Management, Service Management, Customization, Missing Entities, Business Process Flows and Custom Entities.



Privileges

Privileges define what action a user can perform in VeloCITY. Privileges can be modified but cannot be added or deleted. The default privileges for each entity are:

- Create Allows the user to add a new record
- Read Allows the user to view a record
- Write Allows the user to edit a record
- Delete Allows the user to delete a record
- Append Allows the user to attach other entities to, or associate other entities with a parent record
- Append to Allows the user to attach other entities to, or associate other entities with the record



Levels of Access

There are 5 levels of access for each Privilege and they are shown below them. The 5 levels of access are:

- None No privileges given
- User Privileges to the records owned by the user or shared with the user. Also includes the privileges owned by the team to which the user belongs.
- Business Unit Privileges for all records owned in the business unit to which the user belongs
- Parent: Child Business Unit Privileges for all records owned in the business unit to which the user belongs and to all the child business units subordinate to that business unit
- Organization Privileges for all records in the organization regardless of who owns it

There are 4 base security roles included with VeloCITY 365. Out of the box, users of the system MUST be assigned one, and only one of these base roles.

Base Role	Description	Can Read & Append activities to:	Can Create and Edit	Can Delete
Velocity 365 Agent	Suitable for call center agents or other customer service staff taking phone calls and creating service requests using the Agent Console.	Cases, subscribers, contacts, accounts, interaction (SR) types, tags, alerts & knowledge articles.	Cases, subscribers, contacts, accounts and activities. Can edit my own records and those that have been shared with me.	Nothing
Velocity 365 Back Office	Suitable for departmental users who action service requests and/or assign them for action by others.	Cases, subscribers, contacts, accounts, interaction (SR) types, tags, alerts & knowledge articles.	Cases, subscribers, contacts, accounts, and activities. Typically this role would have full permissions for service requests also.	Nothing
Velocity 365 Admin	Suitable for Configuration Managers who create and manage Interaction (SR) types and other administrative settings such as security.	Cases, subscribers, contacts, accounts, interaction (SR) types, tags, alerts & knowledge articles.	Cases, subscribers, contacts, accounts, interaction (SR) types, tags and alerts.	Cases, contacts, accounts, types, tags and alerts. NOTE: Interaction Types can only be deleted by System Adminstrators
Velocity 365 Read Only	User with only READ permission to the velocity features. May be suitable for senior managers, elected officials, etc.	Cases, contacts, accounts, interaction (SR) types, tags, alerts & knowledge articles.	Nothing	Nothing



In order to provide more granular control over security, there are a number of additional permissions for specific features and functions which can also be granted to any of the roles above (Except the Road Only Role) based on your specific business requirements.

The additional permissions or "Add-on" roles are as follows:

Velocity 365 Add-On Role	Description	Can Read & Append activities to:	Can Create and Edit	Can Delete
Create SR Role	Suitable for someone who can submit new service requests and hence – new cases. NOTE: This is NOT a standard OOTB security role and must be managed separately. Interaction types are related to security roles when they are created and that determines which roles get which permissions. Often it is appropriate to give this role or roles to all of the base roles above (except the read only role).	Service Requests	Service Requests	Nothing
Tag Author	Suitable for someone who can create Tags	Tags	Tags	Nothing
Tag Admin	Suitable for someone who can create AND delete Tags	Tags	Tags	Tags
Alert Author	Suitable for someone who can create Alerts	Alerts	Alerts	Nothing
Alert Admin	Suitable for someone who can create AND delete Alerts.	Alerts	Alerts	Alerts
Content Author	Suitable for someone who authors knowledge articles	Knowledge Articles	Knowledge Articles Note: Can only author, not approve or publish	Nothing
Content Approver	Suitable for someone who approves knowledge articles	Knowledge Articles	Knowledge Articles NOTE: Can approve/reject but not publish	Nothing



Velocity 365 Add-On Role	Description	Can Read append activities to:	Can Create and Edit	Can Delete
Content Publishing	Suitable for someone who publishes knowledge articles	Knowledge Articles	Knowledge Articles	Nothing
Content Admin	Suitable for someone who is a full content manager	Knowledge Articles	Knowledge Articles	Knowledg e Articles
Work Order Read Only	Suitable for someone who needs read-only access to work orders (Requires work order solution)	Work Orders	Nothing	Nothing
Work Order Agent	Suitable for a Field Agent or Back Office user who needs to create and assign Work Orders	Work Orders	Work Orders within their own Business Unit	Nothing
Work Order Admin	Suitable for someone who can manage AND delete Work Orders	Work Orders	Work Orders	Work Orders
ESRI Read Only	Suitable for someone who needs read-only access to ESRI Map records	ESRI Map, Map Layers, Server, Settings and Service Areas	Nothing	Nothing
ESRI Author	Suitable for someone who creates and manages ESRI Map Records	ESRI Map, Map Laters, Server, Settings and Service Areas	ESRI Map, Map Laters, Server, Settings and Service Areas	Nothing
ESRI Admin	Suitable for someone who can manage AND delete ESRI Map Records. NOTE: This role MUST be added to the Velocity Admin role in order to succesully create Interaction (SR) Types.	ESRI Map, Map Laters, Server, Settings and Service Areas	ESRI Map, Map Laters, Server, Settings and Service Areas	ESRI Map, Map Laters, Server, Settings and Service Areas



Velocity 365 Add- On Role	Description	Can Read append activities to:	Can Create and Edit	Can Delete
Cityworks Read Only	Suitable for someone who needs read-only access to Cityworks integration records	Cityworks integration log, integration mapping, integration status mapping and server	Nothing	Nothing
Cityworks Author	Suitable for someone who creates and manages Cityworks integration records	Cityworks integration log, integration mapping, integration status mapping and server	Cityworks integration log, integration mapping, integration status mapping and server	Nothing
Cityworks Admin	Suitable for someone who can manage AND delete Cityworks integration records	Cityworks integration log, integration mapping, integration status mapping and server	Cityworks integration log, integration mapping, integration status mapping and server	Cityworks integration log, integration mapping, integration status mapping and server
Portal Read Only	Suitable for someone who needs read only access to Portal Entities	Portal Entities	Nothing	Nothing
Portal Admin	Suitable for someone who can manage Portal Entities NOTE: This role MUST be added to the Velocity Admin role in order to succesully create Interaction (SR) Types.	Portal Entities	Entity Form, Content Snippet, Entity Form Metadata, Entity Permission & Web file	Nothing



Assigning Security Roles

Every user must have a Security Role assigned

Assigning a Security Role to a user:

Navigate to Settings → Security → Users. The Users grid displays.

Select the user. The User Form for the selected user displays.

Click "Manage Roles" from the form navigation bar. The Manage User Roles dialogue displays.

Select desired roles and click OK.

Assigning a Security Role to a team:

Navigate to Settings → Security → Teams. The Team grid displays.

Select the team. The Team Details Form displays.

Click "Manage Roles" from the form navigation bar. The Manage User Roles dialogue displays.

Select desired roles and click OK.

Assigning a role to a team will automatically apply the same privileges to any user or queue within that team.


Assigning a role to a Business Unit's default team will automatically apply to all users in that Business Unit.



ArcGIS Configuration


There are 5 components for configuring VeloCITY365 to display maps and map information. These components are specific to VeloCITY365 but are closely aligned with ESRI ArcGIS.

The ESRI configuration from a technical viewpoint:





The ESRI configuration from a presentation viewpoint:



- User Input Toolbar enables user to select and location or draw an area.
- Primary Layer Velocity365 adds this to all maps provisioned for user input and sits on top of all other layers. There is no administrator configuration for this layer
- Server Data The layer that displays information from D365 records.
- Other Layers The additional information that has been decided should also be seen. It is seen "on top" of the Base Map.
- Base Map The primary information that the citizens or CSR will see.

The Sample Intake Map and Sample Service Request Map are included for reference.

Do not modify or delete sample settings. It is best practice to deactivate the sample maps and keep them for reference. You can duplicate the maps and modify the duplicates to meet your needs



Sample Intake Map Settings			
Configuration Type	Name	Description	
ESRI Setting	Sample Intake Map Settings	Top level of configuration.	
ESRI Server	Sample Server	By default, use public ESRI servers. Must be configured with client information.	
ESRI Map	Sample Intake Map	Configured for displaying multiple active Case records at once.	
ESRI Map Layer	Sample Intake Map Primary Layer	The layer where location can be entered.	
ESRI Entity Field Mapping	Interaction Type Mapping (New)	Fields relevant for plotting Interaction records on map.	

Sample Service Request Map Settings			
Configuration Type	Name	Description	
ESRI Setting	Sample Service Requests Map Settings	Top level of configuration.	
ESRI Server	Sample Server	By default, use public ESRI servers. Must be configured with client information.	
ESRI Map	Sample Service Requests Map	Configured for displaying multiple active Case records at once.	
ESRI Map Layer	Sample Service Requests Map Primary Layer	The layer where Case points will be displayed.	
ESRI Entity Field Mapping	Velocity 365 Case Field Mapping	Fields relevant for plotting Case records on map.	



Configuring the ESRI Settings

ESRI Settings are the top level of configuration and act as a container for all map-related settings. The purpose of the settings is to provide a naming so you can refer to the underlying components by an identifier. While ESRI Settings are the top level for configuration, you must setup the ESRI Server first.

To Setup the ESRI settings,

- 1. Navigate to Connect 365 → ESRI Settings. The ESRI Settings form displays.
- 2. Click New. The New ESRI form displays.
- 3. Enter the name of the ESRI setting.

 Note The name of the setting is used only for administrator reference and so it is safe to change.
- 4. Select the appropriate server from the Server lookup field

 Note If the Server lookup is empty, you need to setup the ESRI Server.
- 5. Select the appropriate map from the Map field

Setting up the ESRI Server

The ESRI Server setup is required to establish a connection to an ArcGIS server and support public ESRI servers and self-hosted (private) ArcGIS servers.

If using ArcGIS Online the ESRI servers require application registration and may incur charges. Details on how to register with ArcGIS can be found here.

To setup the ESRI settings,

Navigate to Connect 365 → ESRI Servers. The ESRI Servers form displays. Click New. The New ESRI Server form displays. Complete the fields.

Name	Description
Name	The descriptive name of the Server.
	The name of the custom entity.
Is Private Server	Determines is the server configuration is private or
	public. True = Private ; False = Public
	Self-hosted ArcGIS servers must be accessible from internet
	Self-hosted ArcGIS servers can be open (no authentication) or closed (authentication required) Users are never prompted for credentials



Name	Description
Client Id	The client_id is a public identifier for apps. Input the client id generated by ESRI. Once you register the application as per the instruction here . ESRI will generate Client ID and Client Secret for this application. Note: It is NOT recommended to use the same Client Id across environments.
Client Secret	The client secret is a secret known only to the application and the authorization server Input the client secret generated by ESRI. Once you register the application as per the instruction here . ESRI will generate Client ID and Client Secret for this application.
Application Token	When using ESRI ArcGIS Online servers, the ArcGIS web services are secured using ArcGIS token-based authentication; as a result, every request to a resource must be accompanied by a valid token.
Token Expiry Date Time	Used to store the ESRI token expiry date and time. The system checks this field for the expiry date/time and if it is expired or if it is expiring in next 10 minutes, the system will update the token before the map is loaded.
Geocode RestURL Displays if Is Private Server selected	Used to search for an address using the search widget.
Reverse Geocode Rest URL Displays if Is Private Server selected	Used to determine the return address for a point location on a map
Token URL Displays if Is Private Server selected	Used to generate the tokens that will be used to validate addresses.



Configuring the ESRI Map

Setting up an ESRI map determines the map that the citizen will see when they log on to the portal. It is the top level of configuration and acts as a container for all map-related settings. There are a couple of points that are helpful when setting up the maps

- The settings are for the general appearance and feature set of a single map
- The maps are reusable can be shared amongst multiple ESRI Settings records
- While ESRI Settings are the top level for configuration, you must setup the ESRI Server first.

To setup the ESRI settings,

Navigate to Connect 365 → ESRI Maps.

The ESRI Maps form displays.

Click New.

The New ESRI Map form displays.

Complete the fields.

Name	Description
Name	Name of the ESRI map
Description	Description of the ESRI map
Map Features	
Enable Locate Widget	Determines if the map can find the person's current
	location. Determines if the Locate Widget is enabled. Yes
	= Enabled; No = Not Enabled
	The widget will not enable if the client portal is not using a HTTPS website.
Locate Position	The position in the view at which to add the component. If
	not specified, manual is used by default. Known Values:
	top-left top-right bottom-left bottom-right manual
Enable Zoom Widget	Determines if the person may adjust the zoom of the
	map. Determines if the Zoom Widget is enabled. Yes =
	Enabled; No = Not Enabled
Zoom Position	The position in the view at which to add the component. If
	not specified, manual is used by default. Known Values:
	top-left top-right bottom-left bottom-right manual
Enable Home Widget	Determines if the person may easily return to the default
	view of the map. Determines if the Home Widget is
Home Desition	enabled. Yes = Enabled; No = Not Enabled
Home Position	The position in the view at which to add the component. If
	not specified, manual is used by default. Known Values:
	top-left top-right bottom-left bottom-right manual



Map Sketch And Search Tools Settings	
Tool Position	The position in the view at which to add the component. If not specified, manual is used by default. Known Values: top-left top-right bottom-left bottom-right manual
Enable Search Widget	Determines if the Search Widget is enabled. Yes = Enabled; No = Not Enabled
Search Country Code	Determines the country within which the search will be limited. For example, Canada = CAN or CA, United States = USA or US. Additional Country codes can be found here , or by searching for ArcGIS Geocode Coverage
Enable Intersections	Determines if the map will support finding an intersection from the clicking on the map. When enabled, the Intersection tool displays. Yes = Enabled; No = Not Enabled
Intersection Button Label	Determines the label associated with the Intersection tool, i.e., Intersect
Intersection Distance (Meter)	Determines the search radius for an intersection, i.e., distance within X meters. Minimum value = 1 and Maximum value = 10
Intersection Tool Information	Determines the guiding text that displays on the map when the Intersection Tool is selected. For example, Click in the map to find the nearest intersection. Cliquez sur la carte pour trouver l'intersection la plus proche. If the information should display in multiple languages, enter the language versions within the field. If multiple languages are entered, do not separate the languages by a line break.
Intersection Not Found Message	Determines the text that display on the map when an intersection cannot be found within the parameters set in the Intersection Distance (Metre) field. For example, Intersection not found within 2 meters. Intersection introuvable à moins de 2 mètres
Intersection Button CSS Class	Determines the icon used on the Intersection Tool button. Additional icons can be found on the ESRI GitHub, here .



	If replacing the icon, only replace the content displayed underlined and italicized as shown in the
	example. For example, action-button esri-icon- <u>plus-circled</u> esri- component
Clear Button Label	Determines the label associated with the Clear tool, i.e., Clear
Clear Button CSS Class	Determines the icon used on the Clear Tool button. The icon used when delivered is, action-button esri-icontrash Additional icons can be found on the ESRI GitHub, here. If replacing the icon, only replace the content displayed underlined and italicized as shown in the example. For example, action-button esri-icon-plus-circled esricomponent
Enable Push Pins	Determines if the Push Pins are enabled. Yes = Enabled; No = Not Enabled
Push Pin Button Label	Determines the label associated with the Push Pin tool, i.e., Point
Push Pin Tool Information	Determines the guiding text that displays on the map when the Push Pin Tool is selected. For example, Drop the pin in the map. If the information should display in multiple languages, enter the language versions within the field. If multiple languages are entered, do not separate the languages by a line break.
Address Not Found Message	Determines the text that display on the map when an address cannot be found in the location where the pin was dropped. For example, Address not found on selected location.
Push Pin Button CSS Class	Determines the icon used on the Clear Tool button. Additional icons can be found on the ESRI GitHub, here. If replacing the icon, only replace the content displayed underlined and italicized as shown in the example. For example, action-button esri-icon-plus-circled esri-component
Enable Polygon	Determines if the Polygon tool is enabled. Yes = Enabled; No = Not Enabled
Polygon Button Label	Determines the label associated with the Polygon tool, i.e., Polygon



Polygon Tool Information	Determines the guiding text that displays on the map when the Polygon Tool is selected. For example, Draw in the map. Double click to finish. If the information should display in multiple languages, enter the language versions within the field. If multiple languages are entered, do not separate the languages by a line break
Polygon Out of Boundary	Determines the text that displays on the map when a
	location is outside the boundaries of the Polygon. For
	example, This location is outside the city boundary.
	If the information should display in multiple languages, enter the language versions within the field. If multiple languages are entered, do not separate the languages by a line break
Polygon Button CSS Class	Determines the icon used on the Polygon Tool button.
	Additional icons can be found on the ESRI GitHub, <u>here</u> .
	If replacing the icon, only replace the content displayed underlined and italicized as shown in the example. For example, action-button esri-icon-plus-circled esri-component
Enable Address Validation	Determines if Address Validation is enabled. Yes = Enabled; No = Not Enabled
Address Validation Message	Determines the text that displays on the map when a location without a known address is entered on the map. For example, You selected a point that does not have an address do you wish to keep the point or select a new address?
	If the information should display in multiple languages, enter the language versions within the field. If multiple languages are entered, do not separate the languages by a line break. This message will display to citizens if the ArcGIS account has no more tokens. To ensure this does not happen, the ArcGIS account must be maintained.
Consent Title	Determines the label associated with the message that displays when a location without an address is selected for a pin drop, i.e., User Consent.



Accept Button Text	Determines the label associated with the Accept button, i.e., Accept
Decline Button Text	Determines the label associated with the Decline button tool, i.e., Deny
Accept Button Class Name	Determines the icon used on the Accept Button.
	Additional icons can be found on the ESRI GitHub, <u>here</u> .
	If replacing the icon, only replace the content displayed underlined and italicized as shown in the example.
	For example, action-button esri-icon- <u>plus-circled</u> esri- component
Decline Button Class Name	Determines the icon used on the Decline Button.
	Additional icons can be found on the ESRI GitHub, <u>here</u> .
	If replacing the icon, only replace the content displayed underlined and italicized as shown in the example. For example, action-button esri-icon-plus-circled esricomponent
Show Attribution	Determines is the map detail information displays below the map or not: Yes = Visible; No = Not Visible.
Primary Layer	Determines the map layer on which pins will be dropped, i.e., pins are dropped on layers and not on the actual map. While there can be multiple layers on a map, every map must have a Primary Layer.
	Select the Primary Layer to be used on the map from the ESRI Map Layer Lookup.
	The names of the map layers have no impact on the functionality of the layer. Ensure that the layers are named intuitively so they may be easily identified. There is no Administrative configuration needed for this field.
Map Layers sub-grid	Determines all of the map layers that are associated with a map. To add additional map layers, select the Add ESRI Map Layer Record button (+) and select the appropriate layer from the look-up.



Map View Configuration	
Basemaps	Determines the base map that will be shown to the citizen. A sample value for this field is "streets." Additional values can be found here .
Center Latitude	Determines the latitudinal center of the map for the citizen. Contact your ArcGIS manager if assistance is needed to determine this value. For example, the latitudinal center of Toronto could be 43.653200
Center Longitude	Determines the longitudinal center of the map for the citizen. Contact your ArcGIS manager if assistance is needed to determine this value. For example, the longitudinal center of Toronto could be -79.383200
Initial Zoom	Determines the how close or far the map displays for the citizen. The size of the area will help to determine this value. Some trial and error will be needed to determine this value. Typically, however, 10 is a good value.
Min Zoom	Determines the how close a citizen may zoom into the map. The size of the area will help to determine this value. Some trial and error will be needed to determine this value. Typically, however, 0 is a good value.
Max Zoom	Determines the how far away a citizen may zoom out of the map. The size of the area will help to determine this value. Some trial and error will be needed to determine this value. Typically, however, 30 is a good value.
Geological Boundary Settings	
Active Boundary Type	Determines Boundary Type for current map settings. VeloCITY 365 validates the location details returned from ESRI against the location details configured here. If the details match, a pin drop allowed. The selection options are:
	 Feature Layer – the boundaries are determined based on the map layer identified as the feature layer when determining the map layers



	 Polygon – the boundaries are based on the values entered into the Polygon Boundary field. Enter string values for longitude and latitude "[-79.54388, 43.58759]". This field displays once Polygon is selected. Area/Region – the boundaries are based on the values entered into the Country Code, State/Province, City, and Neighbourhood fields (in that order). These values are validated with the result set returned from the ESRI ArcGIS server. These fields display once Area/Region is selected
Out of Boundary Message	Determines the text that displays on the map when a location outside of the determined area is entered on the map. For example, Selected location is out of city limits. Please select location within city limits. If the information should display in multiple languages, enter the language versions within the field. If multiple languages are entered, do not separate the languages by a line break
Country Code (displays when Area/Region is selected within the Active Boundary Type field)	Determines the country within which the search will be limited. For example, Canada = CAN or CA, United States = USA or US. Additional Country codes can be found here , or by searching for ArcGIS Geocode Coverage
State/Province (displays when Area/Region is selected within the Active Boundary Type field)	Determines the state/province within which the search will be limited. For example, Alberta = AB, Texas = TX.
City (displays when Area/Region is selected within the Active Boundary Type field)	Determines the city within which the search will be limited. For example, Toronto or Houston.
Neighborhood (displays when Area/Region is selected within the Active Boundary Type field)	Determines if the neighborhood will be validated when the address is returned from ArcGIS. Refer to the Active Boundary Type field for more information
Invalid Boundary Config Message (displays when Area/Region is selected within the Active Boundary Type field)	Determines the text that displays on the boundary has been configured incorrectly. For example, Out of City If the information should display in multiple languages, enter the language versions within the field.



	If multiple languages are entered, do not separate the languages by a line break
Polygon Boundary (displays when Polygon is selected within the Active Boundary Type field)	Determines the boundaries of the Polygon within which the addresses will be limited. The coordinates must be within a latitude / longitude format, i.e., [-79.54388,43.58759];[-79.54388,43.58957; The coordinates are generated on the client's ESRI account and not provided within VeloCITY 365.
Boundary Marker Style	Determines how the line style which will used to identify the boundary.
Boundary Marker Color	Determines how the line color which will used to identify the boundary.
Boundary Outline Width (px)	Determines how the line width which will used to identify the boundary. The value entered impacts the displays once Polygon is selected from the Active Boundary Type field.
Default Graphic Setting	
Durch win Trung	
Pushpin Type	Determines if the push pin will display as a Marker or as an image.
Pushpin Image (WebResource/dataUrl)	
	an image. Determines the image that will be used if Image has been selected in the Pushpin Type field. The URL to Web
Pushpin Image (WebResource/dataUrl)	an image. Determines the image that will be used if Image has been selected in the Pushpin Type field. The URL to Web resource for the image must be entered
Pushpin Image (WebResource/dataUrl) Pushpin Height (px)	an image. Determines the image that will be used if Image has been selected in the Pushpin Type field. The URL to Web resource for the image must be entered Determines the height of the pushpin image



Pushpin Marker Size (px)	Determines the size of the pushpin if Marker was selected in the Pushpin Type field
Polygon Symbol Style	Determines the symbol style of the polygon if Polygon was selected in the Active Boundary Type field.
Polygon Symbol Color	Determines the symbol color of the polygon if Polygon was selected in the Active Boundary Type field.
Polygon Outline Style	Determines the outline line style of the polygon if Polygon was selected in the Active Boundary Type field.
Polygon Outline Color	Determines the outline line color of the polygon if Polygon was selected in the Active Boundary Type field.
Polygon Outline Width (px)	Determines the outline line width of the polygon if Polygon was selected in the Active Boundary Type field.



Configuring the ESRI Map Layers

Layers are the mechanism used to display geographic datasets in your maps; layers provide the needed detail above and beyond the typical base map. Each layer references a dataset and specifies how that dataset is portrayed using symbols and text labels. Examples of layers: all campgrounds with outlines of individual campgrounds, locations of all known wild fires, park facilities (washrooms, water fountains, benches, etc). When you add a layer to a map, you specify its dataset and set its map symbols and labeling properties.

To setup the ESRI Map Layer setting:

Navigate to Connect 365 \rightarrow ESRI Maps Layers. The ESRI Map Layers form displays. Click New. The New ESRI Map Layer form displays. Complete the fields.

Name	Description	
Name	Determines the name of the custom entity.	
Title	Determines the title of the layer. The title is used to identify each layer in places such as the Legend and Layer List Widget.	
Layer Type	 Determines the Layer Type by defining the layer shown on the map. The layer type options are: Feature Layer – Allows client-side processing, popup templates, renderers with 2D and 3D symbols, and querying Its limitations include a limited number of features for display; the possibility of large downloads depending on number of features. Graphics Layer – Allows the storing of points, polylines and polygons in a single layer. No geometry schema Its limitations include no renderer nor popup templates; visualization and popup templates are handled on a graphic-by-graphic basis. CSV Layer - Allows client-side processing, popup templates, and renderers with 2D and 3D symbols. Its limitations include the possibility of large downloads depending on the number of features Tile Layer – Allows better performance if using large datasets and has querying features. Its limitations include no editing, client-side rendering, or popup templates; some schema limitations in 3D views. Vector Tile Layer – Allows features to be styled client-side and used as a tiled basemap. Its limitations 	



	include no editing, client-side rendering, or popup templates.
Data Source	Determines the data source for current layer and is dependent on the value selected within the Layer Type field.
Opacity	Determines if the layer is visible to the citizen or not. This value can range between 1 and 0, where 0 is 100 percent transparent and 1 is completely opaque.
Sort Order	Determines the order in which the layer will be drawn on a particular map. The possible sort order values are between 0 to 10,000
Visible	Determines if the layer is visible or not. Yes = Visible and No = Not Visible. Set this value to No if you don't want the system to load the layer on the map. If you set the opacity setting, the system will still load the layer.
Entity Field Mapping	Identifies the Form Field Mapping based on the information on the Field Mapping details configuration
Enable Feature Selection	Determines if the feature selection is enabled or not. Yes
Displays only when Arc GIS Server is selected from the Data Source field.	= Visible and No = Not Visible
Enable Layer Search	Determines if the layer search feature is enabled or not.
Displays only when Arc GIS Server is selected from the Data Source field.	Yes = Visible and No = Not Visible
Enable As Boundary Validation	Determines if the boundary validation is enabled or not.
Displays only when Arc GIS Server is selected from the Data Source field.	Yes = Visible and No = Not Visible
Data Source	
CSV URL	Determines the data sources for the layer.
Is unlocked only when CSV File is selected from the Data Source field.	Unlocked only when CSV File is selected from the Data Source field.
Portal Item	Determines the data sources for the layer.



	Unlocked only when Portal Item is selected from the Data Source field
Service URL	Determines the data sources for the layer. Unlocked only when ArcGIS Server is selected from the Data Source field
Maps	
Maps Sub-grid	Determines the maps to which the layer is associated. The layer record must be saved before the association can be completed.



Configuring the ESRI Layer Field Mappings

Entity layer field mapping can be only added for the ArcGIS Server source layer.

To complete the Layer Configuration for the ESRI Map Layer, Navigate to Velocity → ESRI Map Layers and create a new Layer.

Enter the name and title of the layer
Select "Feature Layer" from the Layer Type dropdown
Identify the Data Source
Enable Feature Selection – this MUST be set to YES
Enable Layer Search – this MUST be set to YES
Enable Layer Field Mapping – this MUST be set to YES

Since we need to capture the layer details for both Service Requests and Case Records, you will set up ONE mapping record and when the fields are created in the Case and the SR Entity, it is critical they have the exact same schema name.

Field Name	Description
Esri Map Layer	Layer with which currently record is associated
Entity Logical Name	Lookup to select Entity
Entity Attribute	Lookup to select attribute from the entity selected in Entity logical Name.
Esri Layer Field Name	Field Name from the actual Feature Layer that we need to capture.

In order to set up these fields and the Entity Layer Field Mapping, you need to follow the following steps.

- 1. Identify layers and interaction types that need to be configured.
- 2. Identify the fields for each layer that need to be configured.
- 3. Create fields in both the Interaction Type Entity and the Case Entity
- 4. Update the Agent, Manager and Webforms
- 5. Create Layer field mapping for each layer.
- 6. Modify the OOB workflow to sync these fields.



Configuring the ESRI Entity Field Mappings

Entity field mapping is determining where information will be stored within CRM. For example, citizen input (location of a service request) or data (location of an active case) plotted on the map. The field mapping is referenced by the ESRI Map Layer. In addition, the mapping can be shared amongst multiple ESRI Map Layer records and records types with similar schema, i.e., Interaction Types.

To setup the ESRI Map Layer setting:

Navigate to Connect 365 → ESRI Entity Field Mappings. The ESRI Entity Field Mappings form displays.

Click New. The New ESRI Entity Field Mappings form displays.

Enter an intuitive name for the mapping in the Name field.

Select an entity from the right-hand Entity Logical Name lookup field. The left-hand Entity Logical Name text field populates.

Select an entity from the right-hand column field. The left-hand text field populates and is editable.

Input information into the text fields on the left side of the form

Select the destination fields from the look-ups on the right side of the form.

There are 2 field mapping scenarios with typical settings in the table below

Field Name	Typical Values for Contact Field Mapping	Typical Values for Case Field Mapping
Location Field	abs_formattedaddress.	abs_location1_address1
Latitude Field	address1_latitude.	abs_location1_address1_latitude
Longitude Field	address1_longitude.	abs_location1_address1_longitude
Street Address Field	address1_line1.	abs_location1_address1_line1
City Field	address1_city.	abs_location1_address1_city
State / Province Field	address1_stateorprovince.	abs_location1_address1_stateorprovince
Postal Code Field	address1_postalcode.	abs_location1_address1_postalcode
County Field	address1_county	abs_location1_address1_county
Neighborhood Field	Not used on Contacts	abs_location1_address1_neighbourhood
Country Field	address1_country	abs_location1_address1_country
Polygon Field	Not used on Contacts	abs_polygonsettings



Configuring Service Areas

Service Areas are used to define specific geographic regions to facilitate routing of service requests, assist in more detailed reporting and identify areas where resources are either under or over utilized.

To set up a service area, navigate to Velocity \rightarrow ArcGIS \rightarrow Service Areas

Click new

Add the name of the service area

Identify the boundary type (Pin, Polygon, Feature Layer)

For a Pin, you can define the pin on the map and then define a radius around the pin

For Polygon, you can draw the polygon on the map (Example: a Park)

For Feature Layer, you can identify the url for the feature layer. (Example: all the Parks within a community)

Identify the restriction

Prevent SR creation in this service area

Restrict SR creation to within this service area

No restriction (this is typically used when you want to use the service area for reporting and not necessarily use it for routing service requests)

Identify the Routing Team and the Routing Queue

Service area type

Ward – this is a specific service area type used to define wards within the community. Typically you would need to add one service area of the Ward type for each unique ward within your community. Other

Enable for CRM

Indicates if this service area applies to the CRM map settings. This means that the service area will be displayed and used on maps displayed on CRM when the interaction type includes this service area.

Enable for Portal

Indicates if this service area applies to the Portal map settings. When enabled this service area will be used on the portal maps that include the interaction type with this service area.

Configuring Icons

The icons that display on the Interaction Type buttons as well as on the map overlays are completely customizable. There are two recommended open source sites for additional imagery:

- Bootstrap v3.x or here
- Font Awesome v4.x or <u>here</u>



Map Settings for Agent Console

The Agent Console contains a map configured to display each service request by Interaction Type. The Agent Console Map Settings are controlled through the ESRI Map Settings.

In order to have the map for the Agent Console you MUST have a Map Setting specifically called "Agent Console." Velocity has this Map Setting already created out of the box. Listed below are the settings that are configurable for the Agent Console Map. *All other settings will have no effect on the map and should not be changed.*

To change these settings, navigate to Velocity → ArcGIS →ESRI Settings → Agent Console → then click on the Agent Console Map Settings link

Map Features

- Enable Zoom
- Zoom Position
- Enable Home Widget
- Home Position

Map View Configuration

- Basemap Color
- Center Longitude and Latitude
- Initial Zoom
- Minimum Zoom
- Maximum Zoom

Default Graphic Settings

- Push Pin Settings
 - Pushpin Marker Style (default is circle)
 - Pushpin Marker Color (Enter the appropriate hex code for the color you want)
 - Pushpin marker size (Pixels)
- Polygon Settings
 - Polygon Symbol Style
 - Polygon Symbol Color
 - Polygon Outline Style
 - Polygon Outline Color
 - Polygon Outline Width (Pixels)

The following list of features are intentionally unsupported on the Agent Console Map and should NOT be changed:

Locate Widget
Sketch Tools (Intersections, Pins, and Polygons)
Search Widget
Address Validation
Map Boundary
Enable as Boundary Layer Validation (The boundary will appear, but no validation will happen)

Feature Layer Field Mappings.



Map Settings for Portal Service Request Map

The map displays the service requests that have already been submitted. When a request is submitted, it is saved within VeloCITY as a case record. The settings for the map are to display

- Case records whose Interaction Type is flagged with public visibility
- Active Cases created within last 7 days

To change the ESRI Map Settings for the Portal Service Request Map,

Navigate to Connect 365 → ESRI Servers.

The ESRI Servers form displays.

Click Email A Link.


A new email with the link to the Sample Service Requests Map Settings displays.

Copy the portion of the link shown in bold and underlined.

https://adoxio-velocity365-

portaltest2.crm.dynamics.com/main.aspx?etc=10010&extraqs=formid%3d6fb393d7-b4a5-49be-b032-a169e8fd9588&id=%7bB021AD4A-3D6B-E811-8128-

5065F38A6BF2%7d&pagetype=entityrecord



Navigate to Portals \rightarrow Site Settings \rightarrow Velocity365/ServiceRequestMap/EsriMapId. Locate the Value field and paste the copied portion of the link. Save



Citizen Engagement Portal Configuration

The Citizen Engagement Portal allows citizens to self-serve both the receiving and the reporting of information. The details of both the push and pull is highly configurable. The configuration of the portal provides the opportunity to decide how, when, and what the citizens will experience when they visit.

- The **how** is developed through authentication, and deciding the scope and depth of information available to citizens prior to your knowing who they are. The technical aspects are:
 - Authentication
 - Web Roles
- The **when** is deciding the circumstances that will encourage citizens to visit as well as when information that will be provided. The technical aspects are
 - Service Request Navigation
 - Content Management
- The what is the content (both text and visual) within the portal. The technical aspects are:
 - Branding and Theming
 - Web Templates
 - Portal Content

Portal Authentication

The portal can be setup to be either anonymous or to require authentication. If authentication is required, note that it is contact-based and so administrators will need to be assigned a web role with permissions to update the portal. While authentication can be either Local Authentication or External Authentication, we strongly recommend the Azure B2C option.

For more information on portal authentication, refer to the Microsoft website and search for "Configure Dynamics 365 portal authentication", or click here.

For more information on restricting page content to specific citizens, refer to the Microsoft website and search for "Control webpage access for portals", or click here.



Web Roles

Web roles determine permissions to complete any special actions or access any protected content on the portal. For example, if a page can only be seen if the contact is known, the contact must be assigned to a role allowing access to that page. If the content on a page needs to be updated or a new page created, the contact must be assigned to a role that is given content publishing permissions. There are 3 roles included with an out of the box portal: Administrator, Authenticated Users, and Anonymous Users.

Administrators – The Administrator Role is created for users that should be free from the constraints of either the Authenticated Users Role or the Anonymous Users Role.

Authenticated Users - The "Authenticated Users Role" is the default web role for all authenticated users. This role is commonly used to provide a predetermined access for users that are not associated to any other roles. Keep in mind that users can have multiple web roles, but there can only be one Authenticated Users web role for authenticated users.

Unauthenticated Users - The "Anonymous Users Role" is intended to be used with Entity Permissions. It will not respect any other rules or permissions. By enabling the "Anonymous Users Role" it will become the default web role for all unauthenticated users. There can only be one Anonymous Users web role for unauthenticated users.

To create a new web role:

Navigate to Portals \rightarrow Security \rightarrow Web Roles. The Web Roles grid displays. Click New. The New Web Role form displays. Specify values for the fields provided. Refer to the table. Click Save.

Name	Description
Name	The descriptive name of the Web Role
Website	The website to which the role is associated.
Description	An explanation of the Web Role's purpose. Optional.
Authenticated Users Role	Set to Yes - this will be the default web role for authenticated users. The settings for the 3 typical roles are: Authenticated User – Yes Anonymous User – No Administrators - No Only one Web Role with the Authenticated Users Role attribute set to true should exist for a given website. This will be the default web role for authenticated users that have not been assigned a web role.



Anonymous Users Role	Set to Yes - this will be the default web role for unauthenticated users. The settings for the 3 typical roles are:
	Authenticated User – No Anonymous User – Yes Administrators - No Only one Web Role with the Anonymous Users Role attribute set to true should exist for a given website. This will be the default web role for unauthenticated users. Also note that the Anonymous Users Role will only respect Entity Permissions.



Branding and Theming

The Portal is built using the Bootstrap front-end framework and as a result you can quickly and easily brand the Portal for your organization. Bootstrap includes CSS and JavaScript components for common web application interface elements and includes styles for navigation elements, forms, buttons, and a responsive grid layout system. The update of the bootstrap file will complete the majority of the branding changes and so updating bootstrap is the place to start.

In addition to the bootstrap css there are other web files and templates that will not be identified within the bootstrap framework but can be copied and modified:

- 'Velocity365.css' Web File (+ reference in 'Header' or 'Footer')
- 'Header' Web Template must be referenced by the website record
- 'Footer' Web Template must be referenced by website record
- 'Velocity365/General/StylesAndJavaScriptForNoHeaderFooter' Web Template affects some content inserted asynchronously via IFRAMEs or Ajax
- Additional (add your own) CSS/JavaScript/font Web Files (+ reference in 'Header' or 'Footer')

If you decide to use a custom bootstrap.min.css, you can apply it to your portal by applying the custom Bootstrap theme without modifying the site code by uploading it as a web file

For additional information on customizing your portal search for "Create a theme for your portal" on the Microsoft documentation site or <u>click here</u>.

Updating Web Files

To apply a custom CSS file:

Sign into the portal as an Administrator.

Navigate to the portal's Home page. The editing dialogue displays.

Select Children. The Edit Children dialogue displays.

Navigate to the current CSS file and select the Edit this File (pencil and paper) button to the right of the CSS file that is being edited. The Edit this File form displays.

Select the Choose File button and navigate to the new CSS file and select Open. The name of the selected file displays to the right of the Choose File button.

Enter bootstrap.min.css in the Partial URL field. This value indicates to the Dynamics 365 portal's framework that it should use your custom version of Bootstrap instead of the default version included.

NOTE: Do not replace the velocity365.css file. Rather, copy and deactivate the original file and modify the new file.

Select the Hidden from Sitemap check box (selected by default), so that this file doesn't appear to users on the site.

Select Save.

Refresh the page, and your customized styles will appear immediately.



Updating Web Templates

The web templates within VeloCITY 365 define the reusable content structures. Web templates are used to determine full page layouts, the major boundaries and sections of a page or simple web services/endpoints to small embeddable widgets and contain much of the visual elements and logic that make up Velocity 365. Web Templates can be embedded within one another, for example widgets are small Web Templates containing one or more elements that can be embedded on a page.

VeloCITY 365 integrates an open-source template language called Liquid for templating syntax and HTML, CSS and JavaScript. The use of Liquid allows for server-side logic to determine what is returned to the web browser. Liquid uses a combination of objects, tags, and filters to render dynamic content.

NOTE:

It is very important that you never customize original VeloCITY 365 web templates as this makes upgrades difficult. It is recommended that the templates be copied and then updated so the query functions are available but the page display is updated. Also note that some templates are referenced by name and so the copied templates need to have the same name.

The custom templates and elements can be reused, and so don't store text directly within them.

To customize web templates:

Log into VeloCITY 365 as an Administrator

Navigate to Portals \rightarrow Web Templates. The Web Templates form displays.

Open the web template to be modified and copy the source code.

Click New. The New Web Template form displays.

Enter the required information and paste the code into the Source field.

Name the new web template with a similar and easily recognizable name. Note: some web templates are referenced by name.

Click Save and Close.

Deactivate the original web template.

For more information on portal pages, refer to the Microsoft website and search for "Configure site settings for portals", or click <u>here</u>.

For more information on widgets within this document, refer to the Widgets section 19, or by clicking here



Site Settings

The site settings are configurable records that the portal references to either modify behavior or visual information. There are Global Portal, Portal site and Velocity365 settings. For more information on the Global Portal and Portal site settings, refer to the Microsoft website and search for "Configure site settings for portals", or click here.

The typical Velocity365 settings are:

Name	Value
Velocity365/Alerts/HomePage/Count	2
Velocity365/Alerts/SearchByCreatedOnDaySpan	30
Velocity365/InteractionTypes/TileMenu/DefaultFAicon	fa-circle
Velocity365/InteractionTypes/TileMenu/DefaultImage	https://via.placeholder.com/ 200X200
Velocity365/InteractionTypes/TileMenu/NumberOfLevelsToDisplay	2
Velocity365/InteractionTypes/TileMenu/ShowChildTileIcons	true
Velocity365/InteractionTypes/TileMenu/UseMasonryJs	true
Velocity365/InteractionTypes/TileMenuStyle	Grid
Velocity365/InteractionTypes/TileMenuTitlePosition	DOWN
Velocity365/RelatedWidget/NumberOfRecordsToShow	5
Velocity365/ServiceRequestIntake/DuplicateDetection/GridPageSize	6
Velocity365/ServiceRequestIntake/Location/EsriMap/DefaultMapSettingsId	5CAFB1D6-236B-E811-8128- 5065F38A6BF2
Velocity365/ServiceRequestIntake/Location/EsriMap/MapHeightInPixels	600



Velocity365/ServiceRequestMap/EsriMapId	B021AD4A-3D6B-E811-8128- 5065F38A6BF2
Velocity365/ServiceRequestMap/Filters/DaysToShowByDefault	7
Velocity365/ServiceRequestMap/InteractionTypeLegend/ListItemClasses	fa fa-circle
Velocity365/ServiceRequestMap/MapMarker/DefaultColor	black
Velocity365/ServiceRequestMap/OpenServiceRequestDetailsInNewWindow	true
Velocity365/ServiceRequestMap/ShowChildIteractionTypes	true
Velocity365/Tag/DeflectionColumnPerRow	2
Velocity365/Tag/SearchResultsColumnPerRow	4
Velocity365/Tags/SearchResultsNumberOfRecordsToShow	9



Portal Content

The content within the VeloCITY portal is completely customizable by anyone with Administrator-level permissions. These permissions allow every level of the portal to be edited. There are two types of edit interfaces, content and navigation.

Edits should be made to non-production environments and changes should follow the proper change management process.

The level of security access may differ and so refer to your custom security roles.

How to edit page content

- 1. To edit content on the portal, login using Administrator permissions and navigate to the area or page requiring the updates.
- 2. Hover over the existing content. The Content Edit control displays and click Edit. The Edit secondary window displays.
- 3. Edit the content and/or controls and click Save.

How to edit navigation

- 1. To edit navigation on the portal, login using Administrator permissions and navigate to the area or page requiring the updates.
- 2. Hover over the existing content. The Navigation Edit control displays and click Edit. The Edit secondary window displays.
- 3. Edit the content and/or controls and click Save.